



Firmware upgrade guide

Point of View 8" TAB- PROTAB26 XL

Preparation notice:

Upgrading the firmware of your device may enhance the performance and functionality of your device. Incorrect follow-up of the steps described in this manual can cause irreversible damage to your tablet. Backup all your information before continuing and thoroughly read the instructions before taking action.

- Check if you have downloaded the correct firmware by matching the item number on the back of the tablet.




TAB-PROTAB26XL Firmware Upgrade Instructions

- Backup the personal data on the tablet
- Ensure that the battery is fully charged and you have the AC adapter plugged in
- Be sure to shut down and save your in background running processes.
- Temporary disable your antivirus program before updating your tablet.
- unpack your downloaded update file.
- USB A male > Micro USB B male cable is required
- Connect charger to the tablet and USB cable to the PC and tablet.



- Power off the device



- Note: During Update mode screen will remain black !! => If tablet starts up => shutdown tablet and repeat step below.

TAB-PROTAB26XL Firmware Upgrade Instructions

-Simultainiously press the **Power** button and **Back** button on the tablet for a **few seconds**.



Hold

Hold

Hold


Press 5x quickly

-Now keep the **back** button pressed at all times and release the power button and press the powerbutton 5 times quickly (while still holding the **back** button).

-After the 5 th time you will hear a sound in windows. (you can now release all buttons)

(If nothing happens you can also do the following > Hold both **power+ back** and keep them pressed > Press reset button once > press **power** button 5x times while holding the **back** button)


-In Windows go to Computer and click on right mouse button and select Manage




-In the new opened window Computer Management select Device Manager

-Now right click on the unknown device and select Update Driver Software...

TAB-PROTAB26XL Firmware Upgrade Instructions



-Manually search driver by selecting Browse my computer for driver software.




-Go to the location where you have unpacked the update folder

TAB-PROTAB26XL Firmware Upgrade Instructions

-Browse to the directory where you have extracted(unzipped) the folders, this should be similar to:


C:\PROTAB26XL\UsbDriver



-Note: in most cases if you did not move the folder it should be in your downloads folder =>example:
C:\Users\XXX\Downloads



-Press Next

-When windows asks if you want to install the device software select install



TAB-PROTAB26XL Firmware Upgrade Instructions


-When successful, close the window.



Note: The driver installation only need to be done if this is the first time you update your tablet firmware. If you already have done an update in the past the driver is already installed then you can skip this part and continue updating directly.

TAB-PROTAB26XL Firmware Upgrade Instructions

-Go back to the extracted folder and double click on LiveSuitPack105_english.




-It will now unpack all files in the same folder. Now double click on LiveSuit

Name	Date modified	Type	Size
UsbDriver	12/12/2011 12:18 ...	File folder	
ACmd	12/12/2011 12:18 ...	DLL File	60 KB
APipe	12/12/2011 12:18 ...	DLL File	92 KB
Config	12/12/2011 12:18 ...	DLL File	40 KB
crc32	12/12/2011 12:18 ...	DLL File	32 KB
eFex	12/12/2011 12:18 ...	DLL File	44 KB
encode	12/12/2011 12:18 ...	DLL File	32 KB
filelist	12/12/2011 12:18 ...	Text Document	1 KB
idfactory	12/12/2011 12:18 ...	DLL File	36 KB
ImgDecode	12/12/2011 12:18 ...	DLL File	44 KB
KSDecode	12/12/2011 12:18 ...	DLL File	100 KB
LiveSuit	12/12/2011 12:18 ...	CFG File	1 KB
LiveSuit.dat	12/12/2011 12:18 ...	DAT File	4 KB
LiveSuit	12/12/2011 12:18 ...	Application	1,108 KB
LiveSuitCN	12/12/2011 12:18 ...	Adobe Acrobat D...	363 KB
LiveSuitEN	12/12/2011 12:18 ...	Adobe Acrobat D...	891 KB
LiveSuitPack105_english	4/20/2011 2:55 PM	Application	3,808 KB
LiveSuitTW	12/12/2011 12:18 ...	Adobe Acrobat D...	376 KB
Release_FW	12/12/2011 12:18 ...	DLL File	24 KB

-The following screen will appear. Now press SelectImg to browse to the location where you have unpacked the downloaded files for the Image.

TAB-PROTAB26XL Firmware Upgrade Instructions




- Now unplug the usb cable from the tablet and plug it back into the tablet.
- Wait a moment for windows to recognize the tablet. After this is done the following windows will appear.


TAB-PROTAB26XL Firmware Upgrade Instructions

-Press Yes

Press Yes




LiveSuit will now update your tablet.



-Note: During update do not interrupt this process until this is completely finished interrupting may cause damaged on your tablet !!


-After update is finished press OK



Your Tablet now has been updated and will start up automatically.

TAB-PROTAB26XL Firmware Upgrade Instructions

-Press **Exit** to close the LiveSuit



Press the **Power button** to boot up Your Tablet until the Language selection appears.

Note :First time after booting a upgrade will take a the tablet longer to start up so be patient and do not disrupt this process !!

END